

Technical Information	Date: 18.02.2019 Official: Marier Department: BT-FIR/MKP3
------------------------------	---

Tech. Information No.	2217 / 2019
Subject:	FPA-5000: new firmware 2.21.3 and RPS 4.10.6

Short Description:	New Feature: Network counter compliant with Austrian F3000 Norm Solved Issue: life-time counter compliant with EN54-2 chapter 7.13, FAP-520 „pollution“ only in history log
---------------------------	--

Hardware <input type="checkbox"/>	<input type="checkbox"/> Device	<input type="checkbox"/> Module	<input type="checkbox"/> PCBA
Software <input checked="" type="checkbox"/>	<input checked="" type="checkbox"/> Application	<input type="checkbox"/> Driver / Extension	<input checked="" type="checkbox"/> Firmware

Affected Products (details)	CTN	SAP no.	Aff. version	New version
Main Panel Controller	MPC-xxxx-C	All languages	2.21.2	2.21.3
Main Panel Controller	MPC-xxxx-B	All languages	2.21.2	2.21.3
Main Panel Controller	FPA-1200-MPC-C	All languages	2.21.2	2.21.3
Main Panel Controller	FPA-1200-MPC	All languages	2.21.2	2.21.3
Main Panel Controller	FPA-1100-DE	F.01U.316.057	2.21.2	2.21.3
Remote Keypad	FMR-5000-C	All languages	2.21.2	2.21.3
Remote Keypad	FMR-5000	All languages	2.21.2	2.21.3
FPA configuration tool	FSP-5000-RPS	F.01U.005.615	4.10.3	4.10.6

Number of delivered devices		
Period of delivery	from:	to:
Affected serial numbers	from:	to:

Priority Level	Criterion
I <input type="checkbox"/>	The change has to be made immediately (see dates below)
II <input type="checkbox"/>	The change has to be made during the next inspection.
III <input checked="" type="checkbox"/>	Change has to be made, if the error pattern recurs and with new installations.
None <input type="checkbox"/>	General Information (like new tool, new feature, new SW release)

Action Plan	
<input checked="" type="checkbox"/>	Inform customers
<input type="checkbox"/>	Arrange re-work of stock (CSO)
<input type="checkbox"/>	Arrange re-work of stock (customer)
<input type="checkbox"/>	Arrange re-work of installed products
<input type="checkbox"/>	See detailed actions on following pages

Start Date		Completion Date	
-------------------	--	------------------------	--

New Features

- **Austria F3000 Network Counter**

The Panel Controller fulfills Austrian normative requirements of the F3000 norm, chapter 5.2.4 and 5.2.5 for network counter synchronization. For a complete reset of the alarm counter, a restart of the panel controller is required.

Solved Issues

- **Life time alarm counter**

The life time alarm counter for external alarm records the number of instances that the panel enters the fire alarm condition, see VdS EN54-2, chapter 7.13.

- **Invisible Detectors: "Pollution - Dirty" must not activate the general trouble LED**

Removal of the trouble message shown on panel main display in previous versions for "Pollution" message. Instead, a message is now shown in the History Log only. With "Pollution", the FAP-520 detector is still completely functional.

Notes

- MPC firmware V2.21.3 is compatible with OPC Server 1.4.2 and 1.4.3 and also FSI-lib 1.4.2 and 1.4.3
- Download all technical bulletins (TIs) and released software from the '[ST-FIR Tech Support](#)' sharepoint

(registered users only)

Required Components	Part no.

Attachment(s)

BU Manager	Knauel	Clerk in Charge:	Marier
-------------------	--------	-------------------------	--------

Distribution

Distribution BU FIR Fire Systems	<input checked="" type="checkbox"/> Julian Tersteegen (BT-FIR/QMM), Claudia Majer (BT-FIR/QMM), Knauel Thomas (BT-FIR/MKP BT-FIR/MKT), Heckl Michael (BT-FIR/MKP3) <input checked="" type="checkbox"/> Angstenberger Josef (BT-FIR/MKR-EU) <input checked="" type="checkbox"/> Ong Kah Seong (BT-FIR/MKR-AP), Leonard Hew (BT-FIR/MKR-AP) <input checked="" type="checkbox"/> Paredes Ivan (BT/MKR-LA), Miers Christopher (BT/FIR-MKT) <input checked="" type="checkbox"/> Haug Stefan (BT-FIR/MKR-EU BT-FIR/MKA-EU) <input type="checkbox"/>
Distribution BU SC Intrusion Systems	<input type="checkbox"/> Petricoin Dennis (BT-SC/PAS2 BT-SC/PAS2-MKP), Dobson Roxanne (BT-SC/QMM2), Hupka Peter (BT-SC/PAS2-MKP5), Weissert Thorsten (BT-SC/PAS2-MKP5) <input type="checkbox"/> Kugler Gerhard (BT-SC/MKR6-EU), Berberian Alexandra (BT-SC/MKR-SEF), Shah Dhaval (BT-FIR/MKR-SEM), Gomez Arevalo Olga (BT/SEI-SCM), Malek Michal (BT-SC/MKR-SEP), van den Berg Quintin (BT-SC/MKR-SEZ), Kiselev Grigory (BT-FIR/MKR-SEO), Sonmez Onur (BT-FIR/MKR-SET), Cojocaru Laurentiu (BT-SC/MKR-SEA BT/SEA-SBD2), Riboli Stefano (BT-SC/MKR-SES), El Makhfi Otmane (BT-SC/MKR-SAN), Reuvers Willfried (BT-SC/MKR-SEB), Kuehlewind Uwe (BT-SC/MKR-SEC), Pillai Kiran (BT-SC/MKR-SEU), Karlsson Anders (BT-SC/MKR-SEN) <input type="checkbox"/> Cabral Paula (BT-SC/MKR-LA), Garms Paul (BT-SC/MKR2-NA) <input type="checkbox"/> Premo Mike (BT-SC/PAS2-ENG1), Meichelbeck Markus (BT-SC/PAS2-ENG5) <input type="checkbox"/> Schmidt Michaela (BT/MKW1) <input type="checkbox"/> Klein Alexander (BT/SC-MKI) <input type="checkbox"/>
Other parties affected	<input checked="" type="checkbox"/> Schrimpf Felix (BT-ASA/MKP BT-ASA/MKC) <input checked="" type="checkbox"/> Proyer Konrad (BT-ASA/SRA-EU BT-ASA/SRA2-EU), Dias Andre (BT-ASA/SRA-LA), Wilson Jim (BT-ASA/SRA-NA), Tan Woo Khiang (BT-ASA/SRA-AP) <input checked="" type="checkbox"/> Gill Manjit (BT-ASA/STS-UK) <input checked="" type="checkbox"/> Teleservice Support (SO/OMM1.3-MB) <input checked="" type="checkbox"/> Becker Oliver (BT-IE/PRM1), Goos Irina (BT-IE/PRM1) <input checked="" type="checkbox"/> Adelmann Petra (BT-IE/EAP3) <input type="checkbox"/>